



Bridgepoint CARPET CLEANING System



Zone Perfect



End Zone



Flex



White Lightning



Point Blue



Maxim



Citrus Solv



Traffic Slam



Fab Set

Residential

A Use for: All 5th generation nylon and other synthetic fibers. For Olefin, use formula "C".

PRESPRAY

1 part Zone Perfect to 32 parts hot water
1 oz. Citrus Solv to each gallon of RTU Zone Perfect

EXTRACT

End Zone
Portable: 2 - 4 ounces per 5 gallon water
Truckmount: 1 quart per 5 gallon water
Point Blue (for extra-heavy soil)
Portable: 2 oz. per 5 gallon water
Truckmount: 3 cups per 5 gallon water

B Use for: Wool, berbers, light-colored and carpets with brownout potential.

PRESPRAY

1 part Zone Perfect to 32 parts hot water
1 oz. Citrus Solv to each gallon of RTU Zone Perfect

EXTRACT

End Zone
Portable: 2 - 4 ounces per 5 gallon water
Truckmount: 1 quart per 5 gallon water

C Use for: Olefin (polypropylene), and olefin blends, olefin berber.

PRESPRAY

1 part Traffic Slam to 32 parts hot water
For extreme soil dilute 1 to 24
1 oz. Boost All per gal. hot water (mix this first with hot water then add Traffic Slam)

EXTRACT

Fab Set
Portable: 4 ounces per gallon water
Truckmount: 1 qt. per 5 gal. water (meter high)

FOR EXTRA HEAVY SOIL

End Zone
Portable: 2 - 4 ounces per 5 gallon water
Truckmount: 1 qt. per 5 gal. water

Commercial

D Use for: Medium to heavy soil.

PRESPRAY

1 part Flex to 8 parts hot water

EXTRACT

White Lightning
Portable: 2 ounces per 5 gallon water
Truckmount: 3 cups per 5 gallon water

E Use for: Very heavy soil and grease

PRESPRAY

1 part Flex to 8 parts hot water
2 oz. Citrus Solv to each gallon of RTU Flex

EXTRACT

White Lightning
Portable: 2 ounces per 5 gallon water
Truckmount: 3 cups per 5 gallon water

F Use for: Olefin (polypropylene), and olefin blends, olefin berber.

Note: This is the same as formula "C", residential olefin.

PRESPRAY

1 part Traffic Slam to 32 parts hot water
For extreme soil dilute 1 to 24
1 oz. Boost All per gal. hot water (mix this first w/ hot water then add Traffic Slam)

EXTRACT

Fab Set
Portable: 4 ounces per gallon water
Truckmount: 1 qt. per 5 gal. water (meter high)

FOR EXTRA HEAVY SOIL

End Zone
Portable: 2 - 4 ounces per 5 gallon water
Truckmount: 1 qt. per 5 gal. water

IMPORTANT FOR ALL CATEGORIES

- To increase efficiency use the HydroForce Injection Sprayer to apply pre-sprays. HydroForce directions are found on the pre-spray container.
- Always apply Maxim Protector to enhance soil and stain resistance and profitability.
- Use Air King Air Movers to reduce drying times.

Resources



Carpet Cleaning Technician Training Module

- Narrated PowerPoint based presentation with embedded example and supporting videos
- Interactive quizzes to measure learning
- Spanish and English versions included.



Fab Set

Encapsulation Commercial Carpet Maintenance Procedures



Procedure

- 1 Pre-vacuum the area to be cleaned to remove excess soil.
- 2 Mix one part **Encapuclean Green DS** with sixteen parts water (8 oz. solution with one gallon of water) into your pump-up or electric pressure sprayer.
- 3 Apply the ready-to-use solution as a mist in a consistent overlapping pattern. Use more solution only in heavily soiled areas.
- 4 Agitate the **Encapuclean Green DS** into the carpet with a counter-rotating cylindrical brush agitation machine, a shampoo brush, or a pre-moistened microfiber bonnet pad.



- 5 Allow the cleaning solution to completely dry. Use an **Air King** air mover to reduce drying times
- 6 Vacuum the carpet thoroughly.
- 7 For ongoing maintenance programs consider Bridgepoint **Encapuclean** with **Maxim** which provides the carpet with enhanced soil resistant protection and replenishes the stain resistance of commercial nylon carpet.



Spot and Stain Removal Chart

A. Water-Based Spots (Food & Beverage)

If spot is water-based, such as: chocolate, ketchup, sauces, etc.

↓
Apply **Avenge**

↓
If spot persists...
Apply **Protein Spotter**

↓
If stain remains,
go to **Advanced Stain Removal, System 1**



B. Coffee, Tea, Urine, Feces

Apply **Stain Zone**

↓
Some decaffeinated coffees contain dyes. If the stain stays after using **Stain Zone**, apply **Coffe Stain Remover**

↓
If spot persists...
Apply **Avenge**

↓
If stain remains,
go to **Advanced Stain Removal, System 1** for coffee and tea.

↓
Go to **Advanced Stain Removal, System 2** for urine.



C. Grease or Oil-Based

If spot is grease or oil-based, such as: salad dressing, cosmetics, tar, etc.

↓
Apply **All Solv** or **Solvent Clean**

↓
If spot persists...
Apply **P.I.G.**

↓
Apply **Solvent Clean**

↓
If stain remains,
go to **Advanced Stain Removal, System 2**



D. Unknown

If spot is unidentifiable:

↓
Apply **All Solv** or **Solvent Clean**

↓
If spot persists...
Apply **Avenge**

↓
If stain remains,
go to **Advanced Stain Removal 2**



E. Gum

If spot is gum:

↓
Apply **Gel Break**

↓
If spot persists...
Blot with **Citrus Solv**



F. Rust

If spot is rust:

↓
Apply **T-Rust**

↓
Extract with water



G. Ink

If spot is ink:

↓
Apply **P.I.G.**

↓
Repeat to remove any remaining color pigment.

↓
Apply **All Solv**

↓
Apply **Avenge**

↓
If stain remains,
go to **Advanced Stain Removal System 2**



Odor Removal

Fast Track Carpet Odor Removal Guide

This guide focuses on those odors mostly found in carpet cleaning situations which include but are not limited to urine, meat, fish, blood, body fluids and protein based spots and spills.

Level of Tolerance

Determine the customer's level of tolerance. If cost is an issue, then you may elect to perform a surface treatment, or sub surface treatment only. If complete odor removal is all that is acceptable, then complete restoration may be necessary. Some customers do not want to replace one odor with another, they want to remove odor from the area entirely.

Bio-Modifier System Pleasant Residual Deodorization

SURFACE TREATMENT

1. Locate the area needing treatment.
2. Apply a heavy spray of Bio-Modifier to area.
3. Clean the carpet as normal.
4. Apply a light spray of Bio-Modifier



Bio-Modifier
Produces multiple enzymes to digest odors at the source quickly and effectively.

SUB-SURFACE TREATMENT

1. Locate the area needing treatment.
2. Saturate area with Bio-Modifier down to the pad. Extract with Water Claw.
3. Clean the carpet as normal.
4. Apply a moderate spray of Bio-Modifier over the affected area.



COMPLETE RESTORATION

For complete restoration procedures, attend a Fast Track or IICRC Odor Control Class. Contact your local Bridgepoint Distributor for class schedules.

Hydrocide System No Residual Fragrance

SURFACE TREATMENT

1. Locate the area needing treatment.
2. Apply a heavy spray of Hydrocide mixed at 8 ounces per 1 gallon of water.
3. Clean the carpet as normal.
4. Apply a light spray of previously diluted Hydrocide.



Hydrocide
Contains an odor neutralizer that binds to and absorbs odors no matter what the source.


SUB-SURFACE TREATMENT

1. Locate the area needing treatment.
2. Saturate area with 8 ounces of Hydrocide per gallon of water. Extract with Water Claw. Repeat as necessary.
3. Clean the carpet as normal.
4. Apply a moderate spray of previously diluted Hydrocide over the affected area.



Local Bridgepoint Distributor

Contact Information

 Bridgepoint Systems 4282 W. 590 S., S.L.C., UT 84123
801-261-1282 Toll Free Customer Service: 1-800-794-7425

 interlinksupply™

Interlink Supply 1-800-660-5803 www.InterlinkSupply.com